

# Planting a Balled-&-Burlapped Hemlock

This instruction is for planting balled-and-burlapped hemlocks between 18” and 8’ tall.

## What You’ll Need

<ul style="list-style-type: none"><li>• Sharp-bladed shovel</li><li>• Top soil</li><li>• Mr. Natural Woodland Soil Mix</li><li>• Mr. Natural Worm Castings or Hen Manure or homemade compost</li><li>• Espoma HollyTone (or any slow-release, acid-based fertilizer labeled for azaleas)</li><li>• Ironite granules</li></ul>	<ul style="list-style-type: none"><li>• Soil Moist for water retention</li><li>• MiracleGro Quick Start liquid</li><li>• Imidacloprid 2F / 2L liquid for 5 years of HWA protection <i>or</i> Bayer Advanced Tree &amp; Shrub for 1 year of HWA protection</li><li>• Water</li><li>• Shredded hardwood mulch</li><li>• Bamboo stake &amp; roll of velcro tape</li></ul>
<p><b>Sources:</b> You can get most of these items at stores such as Home Depot, Lowe’s, Walmart, hardware stores and garden centers. In Georgia, you can usually find Mr. Natural Woodland Soil Mix, Worm Castings, and Hen Manure at Leilani’s Gardens in Dawsonville 706-265-3510, Anderson Feed and Supply in Dahlonga 706-864-3364, Ash Brothers Feed &amp; Farm Supply in Cleveland, and Little G’s Garden Center in Cherry Log 706-273-2012. Elsewhere, check your local garden supply stores and on-line to see where they may be purchased. If you can’t find Mr. Natural WSM, you can substitute MiracleGro Moisture Control, available at places like Home Depot, Lowe’s, Ace Hardware, or Walmart. See the <a href="#">Contacts</a> page of our web site for sources of HWA treatment products, or <b>call the Hemlock Help Line 706-429-8010 for information.</b></p> <p><i>Note: Stores/products mentioned above are provided as suggestions only and are not meant as endorsements.</i></p>	

## Choosing and Preparing the Planting Site

Hemlocks prefer semi-shade or at least afternoon shade in a moist but well-drained (not soggy) location. A north- or east-facing slope that is protected from harsh winds and/or near a stream is ideal, but moisture and drainage are the most important factors.

1. **Survey the planting site** and modify it if necessary to ensure a good growing environment.
  - a. When surveying, look for and remove potential hazards such as leftover construction debris, chemical or oil spills, and bits of mortar or limestone that would create alkaline soil conditions.
  - b. Note the texture and structure of the soil, e.g., clay, loam/silt, sand, rocky, etc. Loamy soil or amended clay soil is best for hemlocks.
  - c. Also check for drainage patterns that would cause excessive dryness or soggy conditions. Avoid such areas if possible.
  - d. If soil debris or contamination is a problem, you should either remove the top six to eight inches of soil and replace it with a good grade of topsoil or choose another site. If soil texture and structure are a problem (e.g., too much sand or rock or soil depth too shallow), you should choose another site. If drainage is a problem, you should either plant your tree slightly higher (1” – 2”) than the surrounding ground or choose another site.
2. **Dig a hole** 3 times the width of the container or root ball (i.e., you could place the pot or root ball in the hole 3 times in a triangle) but only 2” deeper than the dirt in the container or the root ball. Pile the removed dirt next to the hole.

*Note: Dig when the soil is either dry or just damp enough to make a clump when compressed; don’t dig when the soil is wet.*
3. **Make special soil amendment mix as follows:**

2 parts Woodland Soil Mix	1 part aged compost (worm castings, hen manure, or homemade)
1 part top soil	1 tblsp HollyTone + 1 tblsp Ironite per gallon of soil

*Note: Hemlocks prefer acidic soil, but the specific pH range varies among different species. Eastern hemlocks (*Tsuga canadensis*) require a pH range of 4.2 to 5.7. The soil in a woodland setting is normally acidic enough but the soil in a residential setting may or may not be within the desired range. If you’re in doubt about the pH of your planting site, contact your local Cooperative Extension Service agent about a soil test. If your soil is more alkaline than it should be, your Extension Agent can provide instructions for amending it.*
4. **Combine the amendment mixture with the native soil** you removed from the planting hole in a ratio of 1/3 amendment mix to 2/3 native soil.



5. **Prepare HWA treatment:** Mix one 1.6-ounce packet of Imidacloprid 75 WSP with 24 ounces of WARM water in a container with a wide mouth and screw top. Shake well until all the product and packet covering are dissolved.
6. Prepare one gallon of **initial watering solution** per gallon of root ball size and *keep it out of the sunlight* until you're ready to use it. With each gallon of water, add 1 capful of Quick Start and ½ ounce of Imidacloprid 2F/2L or 4 oz. of Bayer Advanced T & S.

### Planting the Tree

Hemlock trees are shallow rooted, so the key to successful planting is to be sure it *ends up* “at grade,” i.e., at the same level as it was originally in the ground or pot.

1. **Put 2 – 3 inches of your soil mix** into the bottom of the hole.
2. **Remove the wire or cord** from the ball but do *not* remove the burlap yet. Place the tree in the center of the hole and refill the hole halfway with your soil mix.
3. Then **open the burlap and lay it out flat in the hole** so that no part of the fabric will come in contact with the surface of the ground.
4. While the hole is only half full, **sprinkle a small amount of Soil Moist** water retention crystals all around the roots of the tree (about 1 tsp per gallon of root ball size).
5. **Fill the hole the rest of the way** with your **soil mix** so that it just covers the root ball. Don't bury it any deeper. The tree should be sitting 1" – 2" above grade level at this point. Firm the dirt *gently* with your foot to eliminate air pockets.
6. **Apply 2 – 3 inches of shredded hardwood mulch** (not pine straw) around the tree to conserve moisture, keep the soil temperature stable, and prevent weeds. *Hint:* Don't heap it up like a mulch volcano! Spread the mulch from the trunk out to the drip line, but pull it back a few inches from the trunk to avoid introducing insects or fungal growth.
7. Immediately after planting, **water thoroughly** but slowly, giving about a gallon of the **initial watering mix** per gallon of root ball size. Two or three hours later, firm the dirt again with your foot to eliminate any remaining air pockets and **water again with the initial watering mix**. The tree should now be sitting exactly at grade, level with the surrounding ground. Don't create a “watering saucer” around the tree as this could retain too much water.
8. **Staking a tree** is usually not necessary, but if wind is a problem, place 3 stakes in the ground one or two feet beyond the drip line and use a soft cord (not wire) to tie the tree *loosely*, 2/3 of the way up the stem, so the tree can still sway several inches side to side. Remove these ties after the first year.
9. **During the establishment period** of up to a year, water with plain water once a week if you don't have rainfall that week. Keep the soil uniformly moist -- not too wet or too dry. Use 1 gallon of water per gallon of original root ball size.
10. **Continue HWA protection.** Plan to retreat the tree with an Imidacloprid 75 WSP or Imidacloprid 2F or 2L product every 5<sup>th</sup> year in the spring.
11. **Giving additional fertilizer** after planting is usually not necessary, but if you do, wait until late winter of the following year. Sprinkle close to the trunk and out to the drip line, and be sure to *follow the recommended dosage* on the product label as too much fertilizer can kill a plant. Do not apply lime anywhere near the hemlock.